How do I Find the Host ID or Physical address of my Computer?

Before registering your product and generating the license file, Schlumberger's Software based products requires that you provide host ID information for the host computer that you install the associated license file on,

Identify the host ID of a physical machine

The host ID is the Physical Address (or MAC address) of the main network adapter.

For Windows 7 & Windows 8: Click on Start at the bottom left of the desktop, type "cmd.exe" where it says search programs and files. *Image1*

For Windows 10:

Open a command prompt window (In the search bar at the bottom left of the Desktop screen where it says, "Ask me anything", type "Command Prompt" and press Enter).

Type in: ipconfig /all. Image2

Option 1: ipconfig (Windows)

(1) Open the command prompt (cmd.exe) and enter the command:

ipconfig /all

Click enter for results. Image3

Programs (1) —	
₽ See more results	
cmd	× Shut down +

Image1 – Windows 7/8 command prompt

🛋 Command Prompt			
Microsoft Windows [Version 10.0.14393] (c) 2016 Microsoft Corporation. All rights reserved.			
C:\Users\ DAccnt>ipconfig /all			
Windows IP Configuration			
Host Name			
Ethernet adapter Ethernet 2:			
Media State Media disconnected Connection-specific DNS Suffix . :			

Image2 – enter the command

Connection-s	pecific DNS Suffix . :			
Description	: PANGP Virtua	l Ethernet Adapter		
Physical Add	Physical Address			
DHCP Enabled	WCP Enabled No			
Autoconfigur	ation Enabled : Yes			
thernet adapte	r Ethernet:			
Connection-s	pecific DNS Suffix . : dir.slb.com			
Description	: Intel(R) Eth	ernet Connection I217-LM		
Physical Add	ress : EC-F4-BB-36-	53-78		
DHCP Enabled	Yes			
Autoconfiguration Enabled : Yes				
IPv4 Address				
Subnet Mask		128		
Lease Obtain	ed : Sunday, Nove	mber 5, 2017 7:46:33 AM		
Lease Expire	sNonday, Nove	mber 13, 2017 7:47:10 AM		
Default Gate	way : 163.186.180.	129		
DHCP Server				
DNS Servers		13		
n	163.186.27.2	b		
Primary WINS	Server 163.188.49.1	25		
Secondary WINS Server : 103.188.49.123				
NELPIO2 OVEL	TCPIP Enabled			
/ireless LAN ad	apter Wi-Fi:			
Media State	: Media discon	nected		
Connection-specific DNS Suffix . : dir.slb.com				
Description	: Intel(R) Cen	trino(R) Advanced-N 6235		
Physical Add	ress : C4-D9-87-B2-	C0-DC		
DHCP Enabled				
Autoconfigur	ation Enabled : Yes			
/ireless LAN ad	apter Local Area Connection* 2:			
H-11- 64-4-				
Media State Media disconnected				
Connection-specific DWS Suffix . : Description				
Description Develop1 Add	MICPOSOFT WI	-ri Direct Virtual Adapter		
PMYSICAL ADDRESS				
Autoconfigur	ation Enabled : Yes			
:\Users\EDandr	ey≻getmac ∕v			
onnection Name	Network Adapter Physical Address	Transport Name		
thernet	Intel(R) Ethern EC-F4-BB-36-53-7B	\Device\Tcpip_{12864FAA-19D2-40EF-A7F6-6B20F4BD38E6}		
li-Fi	Intel(R) Centri C4-D9-87-B2-C0-DC	Media disconnected		
thernet 2	PANGP VIrtual E 02-50-41-00-00-01	Media disconnected		
() Ulcone \ EDando	aux			
. tosers (coanor	cy/			

Image3 – Results

For systems that report multiple host IDs, it may be necessary to use **getmac /v** to identify the host ID (i.e. Physical Address) associated with the Ethernet Network Adapter. *Image3*

Every address that says Virtual (normally with many zeros) should not be used.

e.g.- "02-50-41-00-00-01", "PANGP Virtual Ethernet adapter"

Note: - For <u>Laptop</u> users please run the **ipconfig /all** with and without the docking station and identify the physical address that is present in both the outputs of that command.